

Package ‘adbcpostgresql’

May 27, 2025

Title 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' Driver

Version 0.18.0

Description Provides a developer-facing interface to the 'Arrow' Database Connectivity ('ADBC') 'PostgreSQL' driver for the purposes of building high-level database interfaces for users. 'ADBC' <<https://arrow.apache.org/adbc/>> is an API standard for database access libraries that uses 'Arrow' for result sets and query parameters.

License Apache License (>= 2)

Encoding UTF-8

RoxygenNote 7.3.2

SystemRequirements libpq

Suggests nanoarrow, testthat (>= 3.0.0)

Config/testthat/edition 3

Config/build/bootstrap TRUE

URL <https://arrow.apache.org/adbc/current/r/adbcpostgresql/>,
<https://github.com/apache/arrow-adbc>

BugReports <https://github.com/apache/arrow-adbc/issues>

Imports adbcdrivermanager

NeedsCompilation yes

Author Dewey Dunnington [aut, cre] (ORCID:
<<https://orcid.org/0000-0002-9415-4582>>),
Apache Arrow [aut, cph],
Apache Software Foundation [cph]

Maintainer Dewey Dunnington <dewey@dunnington.ca>

Repository CRAN

Date/Publication 2025-05-27 05:40:06 UTC

Contents

adbcpostgresql 2

adbcpostgresql	<i>ADBC PostgreSQL Driver</i>
----------------	-------------------------------

Description

ADBC PostgreSQL Driver

Usage

```
adbcpostgresql()

## S3 method for class 'adbcpostgresql_driver_postgresql'
adbc_database_init(driver, ..., uri)

## S3 method for class 'adbcpostgresql_database'
adbc_connection_init(database, ..., adbc.connection.autocommit = NULL)

## S3 method for class 'adbcpostgresql_connection'
adbc_statement_init(
  connection,
  ...,
  adbc.ingest.target_table = NULL,
  adbc.ingest.mode = NULL
)
```

Arguments

- driverAn [adbc_driver\(\)](#).
- ...Driver-specific options. For the default method, these are named values that are converted to strings.
- uriA URI to a database path (e.g., postgresql://localhost:1234/postgres?user=user&password=pass).
- databaseAn [adbc_database](#).
- adbc.connection.autocommitUse FALSE to disable the default autocommit behaviour.
- connectionAn [adbc_connection](#)
- adbc.ingest.target_tableThe name of the target table for a bulk insert.
- adbc.ingest.modeWhether to create (the default) or append.

Value

An [adbcdrivermanager::adbc_driver\(\)](#)

Examples

```
adbcpostgresql()
```

Index

`adbc_connection`, [2](#)
`adbc_connection_init.adbcpostgresql_database`
 (`adbcpostgresql`), [2](#)
`adbc_database`, [2](#)
`adbc_database_init.adbcpostgresql_driver_postgresql`
 (`adbcpostgresql`), [2](#)
`adbc_driver()`, [2](#)
`adbc_statement_init.adbcpostgresql_connection`
 (`adbcpostgresql`), [2](#)
`adbcdrivermanager::adbc_driver()`, [2](#)
`adbcpostgresql`, [2](#)